

gründl Pattern FILZWOLLE UNI + COLOR

Rucksack

Difficulty level:







Needles:



Quality:

Filzwolle uni + color (Gründl) 100 % virgin wool 50 g / 50 m





10 x

unfelted: approx. 38 cm wide and 52 cm high felted: approx. 28 cm wide and 32 cm high, carry straps approx. 60 cm long

Usage:

Size:

approx. 250 g felt wool uni Cl. 02 (anthracite) and approx. 500 g felt wool colour Cl. 21 (redorange-black multicoloured), 1 pushbutton Ø 30 mm

Sample:

plain right: RSR.: ri S, BR.: le S in Rd.: only ri S Seed stitch:

in Rd. stitch number divisible by 2: 1st Rd.: alternately kn. 1 S ri and 1 S le 2nd Rd.: alternately kn. 1 S le and 1 S ri in R, stitch number divisible by 2: RSR: alternately kn. the ES1S ri and 1S le BR: alternately kn. the ES1S le and 1S ri Edge stitches: drop ri at row start, knt. ri at row end

Stitch test:

(plain right, unfelted): $11 S \times 16 R/Rd. = 10 cm \times 10 cm$ (plain right, felted): $15 S \times 27 R/Rd. = 10 cm \times 10 cm$ (seed stitch, unfelted): 11 S x 20 R/Rd. = 10 cm x 10 cm (seed stitch, felted): $15 S \times 27 R/Rd. = 10 cm \times 10 cm$

Instructions:

For the bottom of the bag, cast on 40 S and 2 ES in Cl. 01 and knt. 20 cm (= 32 R) plain right, then co. the S straight, knt. the S as they occur. For the wall of the rucksack, pick up the S in Cl. 02 from the edges of the bag floor as follows: start with one long side at the marking (see sketch) and pickup up every 42nd S from the long edge and every 18th S from the short edge of the bottom rectangle (= 120 S). Mark the 1st S of each Rd respectively as the start of the round. Now, kn. plain right in Rd. initially 5 cm (= 8 Rd.) in Cl. 02, then end the rucksack wall in Cl. 21. First kn. 44 cm (= 70 Rd.) plain right. In the following Rd. for the holes to pull through the cord, co. S 9, + 10, 33 + 34, 45 + 46, 57 + 58, 69 + 70, 93 + 94, 105 + 106 and 117 + 118 and cast on every 2nd S again over the cast off S in the following round. continue knt. plain right between the cast off S. Knt. another 3 cm (= 5 Rd.) in seed stitch, continuing with the seed stitch. Now knt. the saddle in Cl. 02 in seed stitch. For this, pick up a total of 36 S from the cast-off edge of the rucksack wall over the 4th - 39th S and knt. 35.5 cm (= 64 R). For the curvatures in the 46th R, co. 1 S on each side, rpt, these drops another 1 x in the

following 4 R and 2 x in each 2 nd R (= 28 S). Then co another 2×2 S and 1×3 S in each 2nd R. co. the remaining 14 S straight, continuing the seed stitch. For the carry handle, cast on 4 S plus 2 ES in Cl. 02 and knt. 40 R in the seed stitch, then co. the S straight, continuing with the seed stitch. For each of the two carry handles, cast on 6 S plus 2 ES in Cl. 21 and knt. 81 cm (= 162 R) in the seed stitch, then co. the S straight, continuing with the seed stitch. For the cord to pull the rucksack closed, cast on 180 S in Cl. 02 and immediately co. again in the following row, knt. the S. For a button, knt. a knob as follows: cast on 10 S plus 2 ES in Cl. 21 and knt. 15 R plain right in RSR and BR. then co. the S straight. Pull together the edge of the developed rectangle with the working thread and loosely fill the rectangle with felt wool.

Completion:

Use felt wool for all seams: Sew on the carry handle and carry straps (see sketch). Sew on the button after felting the bag saddle (see image), ideally using sewing thread and a sharp needle for this purpose. For a fastener, sew a pushbutton on the back of the bag saddle and to the rucksack wall. Also only pull the cord through the holes after felting.

Felting:

Felt the rucksack, the button and the cord (alone) in the washing machine at 40°C. To do this, select the colours wash program (2 hrs.) with 800–1000 revolutions when spinning, no economy or short wash program. Add some detergent without optical brighteners or builtin softener. Do not use softener. To support the felting process, add 3 tennis balls to the washing machine. After felting, bring the rucksack into shape immediately and let it dry. Tip: For forming, pull the still damp rucksack over a suitably sized box or wooden block. If the carry straps are too short, these can be pulled to the correct length while they are still damp.

Abbreviations:

Cl. = colour(s)
S = stitch(es)
Rd. = round(s)
R = row(s)
RSR = right-side row(s)
BR. = back row(s)
ri = right
le = left
co. = cast off
lft. = cast off
ES = edge stitch(es)
knt. = knit
rpt. = repeat
i. e. = in each one
boths. = both sides

