

Pattern

FLIPSY

Footstool Cover

Difficulty level:



Needles:

2 x



6-7

3 x



6-7
80 cm

Quality:

Flipsy (Gründl)
100 % Polyester
100 g / 50 m



3 x

Size:

As shown here: Diameter of the cover is approx. 34 cm, height of the cover is approx. 13 cm

Tip: depending on the size and thickness of your cushion work more or less rounds.

Usage:

For a cushion cover in the size given above: approx. 300 g in col. 05 (turquoise)

Tension:

12 sts and 16 rounds to 10 cm measured over stockinette stitch using size 6 mm needles or size needed to achieve given tension.

Tip: The footstool cover needs to be knit closely so it fits properly on the cushion.

Stitch Pattern:

Stockinette Stitch: *in rounds:* k all sts in all rnds. **1 st doubled:** work k1, k1tbl. into 1 stitch in the previous round.

Instructions:

The cushion cover is started in the centre. Cast on 8 sts and divide sts evenly amongst 4 dpns (= 2 sts per needle) and close the round being careful not to twist the sts. Mark the beginning of the rnd and continue to move the marker as you work more rnds.

K all sts without incs in the rnds not given.

Rnd 1: double each st. (= 16 sts)

Rnd 3: double every 2nd st (= 24 sts)

Rnd 5: double every 3rd sts (= 32 sts)

Rnd 7: double every 4th st (= 40 sts)

Rnd 9: double every 5th st (= 48 sts)

Rnd 11: double every 6th st (= 56 sts)

Rnd 13: double every 7th st (= 64 sts)

Rnd 14: divide the sts amongst 8 needles of the 2 sets of dpns (= 8 sts per needle) and continue the incs as established (= in every 2nd rnd double the last st on each needle)

When the diameter of the knit circle (measured slightly stretched) is the same as the diameter of the footstool cushion (as shown here: 27 rnds = 120 sts) continue without incs.

Tip: beg in approx. the 28th rnd use circular needles (divide work onto 2 circular needles and use the 3rd circular needle to knit). Cast off all sts even when the height of the cushion is reached, once again measured slightly stretched (as shown here 13 cm = 25 rnds).

Use the side with the reverse stockinette sts to the outside pushing the fringe towards the outside.

Finishing:

Thread a stable cord, such as a cotton cord, through the cast off edge and place cover evenly onto footstool. Pull the cord taught and tie into a bow so the cover can be taken off and washed as needed.

Abbreviations:

approx. = approximate(ly)

dpn(s) = double pointed needle(s)

k = knit

rnd(s) = round(s)

st(s) = stitch(es)

tbl = through back loop